DuplineSafe USB Programmer GS73800081

Freeware Program



Installation Manual



Table of contents

1.	INT	RODUCTION	2
2.	SYS	TEM REQUIREMENTS	3
	2.1.	Minimum requirements	3
-	2.2.	Recommended requirements	3
3.	Inst	allation of the DuplineSafe USB programmer software	4
4.	Inst	allation of the DuplineSafe USB programmer driver	8
2	4.1.	Error installing COM-port driver	9
5.	Sele	ct COM-port	10
6.	Con	figurations modes	11
e	5.1.	Manually read and program device	12
(5.2.	Automatic programming a DuplineSafe safety system	13



1. INTRODUCTION

The DuplineSafe USB Programmer is an application and a Converter box intended to configure a DuplineSafe system such as DuplineSafe safety relay Output module type number GS 3830 0143 230 and DuplineSafe Safety Input module type number GS 7510 2101x. The configuration settings can be saved and printed. This installation manual describes how to install and configure the DuplineSafe USB Programmer.



2. SYSTEM REQUIREMENTS

The DuplineSafe USB Programmer requires a PC with Windows XP or Windows Vista installed.

2.1. Minimum requirements

1.0 GHz Pentium 3 processor256 MB RAM1 GB free hard disk space

2.2. Recommended requirements

2.0 GHz Pentium 4 processor 1024 MB RAM 10 GB free hard disk space



3. Installation of the DuplineSafe USB programmer software

Insert the CD in the PC. After a few seconds the window below (Figure 1) will automatically pop up. Press the "Install DuplineSafe USB Programmer" to install the DuplineSafe USB Programmer configurations tool.



Figure 1

Press "Run" to start the installation (Figure 2).



Figure 2



Press "Run" (Figure 3) to verify that you want to run the software.



Figure 3

Press "Next" to start the Setup guide.

DuplineSafe USB Programmer	_ 🗆 🛛
Welcome to the DuplineSafe USB Programmer Setup Wizard	
The installer will guide you through the steps required to install DuplineSafe USB F your computer.	'rogrammer on
Freeware Program	
Cancel < Back	Next >

Figure 4



Select as shown below (Figure 5) and press "Next" to install the program in the default directory, or change directory by pressing "Browse".

🛱 DuplineSafe USB Programmer	
Select Installation Folder	
The installer will install DuplineSafe USB Programmer to the following folder.	
To install in this folder, click "Next". To install to a different folder, enter it belo	w or click. "Browse",
D:\Program Files\Carlo Gavazzi\DuplineSafe USB Programmer\	Browse
(Disk Cost
Install DuplineSafe USB Programmer for yourself, or for anyone who uses th	is computer:
• Everyone	
O Just me	
Cancel < Back	Next >

Figure 5

Now the settings for the installation guide is chosen. Start the installation by pressing "Next".



Figure 6



Press "Close" to complete the installation of the DuplineSafe USB Programmer configurations tool.

🛱 DuplineSafe USB Programmer	
Installation Complete	
DuplineSafe USB Programmer has been successfully installed.	
Click "Close" to exit.	
Please use Windows Update to check for any critical updates to the .	NET Framework.
Cancel	Back Close

Figure 7



4. Installation of the DuplineSafe USB programmer driver

The DuplineSafe USB Programmer Converter box is used for communication between the DuplineSafe safety devices and the PC.

Installation

Plug the USB cable into the Converter box and the PC. After a few seconds the PC will announce that new hardware has been found (Figure 8). Press "Next" and the software will now install itself. It takes only a few seconds. Two drivers must be installed.



Figure 8

When the installation is completed, the following window appears (Figure 9). Press "Finish", and the first hardware installation is completed.



Figure 9



After a few seconds the PC will detect the second new hardware (Figure 10). Select as shown above (Figure 8) and press "Next". The software now installs itself. It takes only a few seconds.



Figure 10

When the installation is completed, the following window appears (Figure 11). Press "Finish" and the installation of the Programming box is completed. See the next chapter to select the right COM-port in the program.



Figure 11

4.1. Error installing COM-port driver

If the Wizard fails to install the driver to the Programming box, select manual installation of the driver by activating the "Install driver" on Figure 1.



5. Select COM-port

After the Programming box has been installed, it is necessary to check which COM-port number it has been allocated.

To do that, go to:

Start \rightarrow Control Panel \rightarrow System \rightarrow Hardware \rightarrow Device Manager (see Figure 12).

Under "Port (COM&LPT)" find the "USB Serial Port" and the allocated COM-port number. In this case the Programming box has been allocated the COM-port number 6.



Figure 12

Subsequently, the same COM-port number is selected in the configuration software of the DuplineSafe USB Programmer under Settings \rightarrow Program Settings, as shown below (Figure 13).

robram servings	
elect comport	
The compatitive the GS73900091 is connected to	
)
elect project file folder	
Project file folder:	
D:\Documents and Settings\Rose Faber\Desktop	
Browse	

Figure 13



6. Configurations modes

There are two different modes of operations. Either, the programmer can manually read and program a device, or he can choose to program a DuplineSafe safety system automatically. These modes can be selected by clicking in one of the check boxes under "Select mode" as shown below (Figure 14).

TuplineSafe USB Programmer	
File Settings Help	
Select mode	
Auto Program Salety System	
Program Safety Receiver GS38300143230	
Program Safety Transmitter GS75102101-1	
Dupline	
Bead device	
Program device	

Figure 14



6.1. Manually read and program device

Manually read and program a Safety Receiver is shown below (Figure 15). The Programmer can read a receiver and see its settings. Then he can change settings and reprogram the receiver with the new settings.

Settings Help						
elect mode						
Auto Program Salety System Program Salety Receiver GS38300143230		Channels	1 2	3 4	5 6	7 8
Program Safety Transmitter GS75102101-1	75102101-1	Group A:	Sync	Input	Input	Input
	174. 4	Group B:	Input	Input	Input	Input
		Group C:	Input	Input	Input	Input
		Group D:				
hudding and have	Numbers of channels	Group E:				
	24	Group F:				
	Sync channel	Group G:				
	A1 🕑 💌	Group H:				
Dupline	Generalite state	Group I				
-	Yes	Group J:				
	Vito restant Yes Vito	Group K:				
		Group L:				
		Group M:				
		Group N:				
		Group O:				
		Group P:				
		Connect				
Bead device						
Program douico	Reset					

Figure 15

Manually read and program a Safety Transmitter is shown below (Figure 16). The programmer can read a transmitter and see its settings. Then he can change settings and reprogram the transmitter with the new settings.

e Settings Help		
Select mode		
Select mode Auto Progum Salety System Progum Salety Execute (53300141220) Program Salety Transmitter G975102101-1 Transmitter G975102101-1	Sync channel	Darreli 2 3 4 5 6 7 8 Group A Sync Daret
Bead device		
Program device	Reset	

Figure 16



6.2. Automatic programming a DuplineSafe safety system

The first step in the "Auto Program Safety System" mode is to configure the receiver, so that the system knows the number of transmitters to be programmed. When the configuration is made, press "Go to step 2" as shown below (Figure 17).

Settings help						
elect mode						
] Auto Program Salety System] Program Salety Receiver GS38300143230	Step 1 Configure the	e receive	devi	ce.		
Program Safety Transmitter GS75102101-1		Channels				
	ANTICALCONCERSION		1 2	3 4	5 6	7 8
	BF2.	Group A:	Sync	Input	Input	Input
and and a second s		Group B:	Input	Input	Input	Input
		Group C:	Input	Input	Input	Input
	Numbers of channels	Group D:				
	24	Group E:				
Dunling		Group F;				
Dopine	Sync channel	Group G:				
-	A1 💌	Group H				
	Generate sync	Group I:				
	Yes	Group J:				
	₩ No	Group K:				
	Auto restart	Group L:				
	Yes	Group M:				
	V No	Group N:				
		Group O:				
		Group P:				
Bead device	Beset					
Program douése	Go to Step 2					

Figure 17

Step 2 is to program the devices. The configuration above decides how many devices that needs to be programmed. Connect the device to the USB Converter box and then push the button that represents the device to be programmed. The button turns green when the device has been successfully programmed (Figure 18).



Figure 18